

Liberate | Simplify | Connect www.finbourne.com


Introduction

 Lumipy is a library that makes it easy to use Luminesce as part of the python data science ecosystem

- Designed to...
 - Get your data into pandas with minimal fuss
 - Be used in Jupyter and support interactive data exploration
 - Be familiar and intuitive
 - Be tactile and discoverable

LUMINESCE

BY FINBOURNE







Getting Started

- Installation
 - Available from PyPI

- Authentication:
 - Uses the same infrastructure as our other python SDKs.
 - You have a choice of
 - Secrets File
 - Token and API URL
 - Proxy authentication
 - Environment Variables

pip install dve-lumipy-preview

```
"api" : {
    "tokenUrl": "the okta token url",
    "username": "your okta username",
    "password": "your okta password",
    "clientId": "the client id",
    "clientSecret": "the client secret",
    "lumiApiUrl":
        "https://<ENV>.lusid.com/honeycomb/
}
```



Your First Query – Running a SQL String

- There are three parts
 - Import lumipy
 - Create client object by giving your authentication details
 - Use the client run method with your SQL string and get the result dataframe back

```
import lumipy as lm

client = lm.get_client(
    api_secrets_filename="/path/to/secrets.json"
)

df = client.run(
    "select * from lusid.instrument limit 10"
)
```

 But there is more to lumipy than sending SQL to the client



The Atlas EX NB 2

- An atlas works like the hub for getting at your data
- It's created in the same way as the client
- It has two functions:
 - Exploring the the providers you have available to you and their metadata
 - The starting point for building queries in the fluent syntax

```
import lumipy as lm
atlas = lm.get_atlas(
    api_secrets_filename="/path/to/secrets.json"
)
```

Getting atlas

- Querying data provider metadata...
- Querying direct provider metadata...
- Building atlas...

Done!

Contents:

- 343 data providers
- 25 direct providers



EX NB 2

- All providers are represented as attributes on the atlas
 - You can explore them via tab completion
 - You can print them to see metadata
 - You can also explore each provider's fields in the same way
- You can explore your providers programmatically
 - search_providers will return another atlas of matching providers
 - list_providers will enumerate the providers in an atlas

```
| atlas.lusid_in|
| lusid_instrument|
| lusid_instrument_bond|
| lusid_instrument_bond_writer|
| lusid_instrument_contractfordifference|
| lusid_instrument_contractfordifference_writer|
| lusid_instrument_equity|
| lusid_instrument_equity_writer|
| lusid_instrument_equityoption|
| lusid_instrument_equityoption_writer|
| lusid_instrument_exchangetradedoption
```

```
inst_atlas = atlas.search_providers('instrument')
```

inst_provs = inst_atlas.list_providers()



The Atlas – Scripting Queries

- All queries start with an atlas attribute
- They are used to initialise a provider table object
- Queries are then built from provider objects via method-chaining
- These atlas attributes can be inspected using tab + shift in Jupyter



- The syntax is based on pyspark and pandas with minimal imports.
- Workflow
 - Start with your initialised provider object
 - Select columns from and chain other clauses
 - Start the query by calling .go() and receive a dataframe back
- By chaining methods you're building up the pieces of a SQL query
- You can inspect the underlying SQL with the print_sql method.

```
query.print_sql()
```

Query Scripting – More Basics

- Parameters are given to the atlas attribute
- New columns are given in the select or aggregate methods as keyword args
- Methods corresponding to SQL clauses must be chained in the same order as a normal SQL query
- You don't have to use all the clauses each time.

```
import datetime as dt
inst = atlas.lusid_instrument(
    as_at=dt.datetime(2022, 9, 1)
)
```

```
query = inst.select(
    inst.scope,
    NewColumn=3.1415
).where(
).group_by(
).aggregate(
).having(
).order_by(
).limit(
```

Query Scripting – Case Statements

- Case statements are a series of conditions and values that build up a column
- They are built by starting at the table object and calling the when method
- After that you call the then method
- This is repeated until you optionally call otherwise. That's the end of the sequence
- If no otherwise is specified then the default value will be NULL

```
label = table.when(
    table.cost >= 1000000
).then(
    "millions"
) when (
    (table.cost >= 1000) & (table.cost < 1000000)
).then(
    "thousands"
) when (
    (table.cost >= 100) & (table.cost < 1000)
).then(
    "hundreds"
).otherwise(
    "less than a hundred"
query = table.select('*', Label=label)
```

Query Scripting – Functions

- We wish to avoid all the (many) imports and doc-searching you have to do in Pyspark. You only need the one in Lumipy.
- Functions are used via accessor attributes just like pandas Series' .str and .dt
- The full set of accessors is larger:
 - str string functions
 - dt datetime functions
 - stats stats functions
 - metric distance metrics
 - financial finance-specific functions
 - linreg linear regression functions
 - cume cumulative functions

```
# pandas
pf[pf.PortfolioCode.str.contains('swap')]
```

```
# lumipy
pf.select(
    '*'
).where(
    pf.portfolio_code.str.contains('swap')
)
```

median = ar.duration.stats.quantile(0.5)

```
ar.duration.stats.quantile()

Signature: ar.duration.stats.quantile(q: float) -> lumipy.query.expression.cotumn-
_op.aggregation_op.Quantile
Docstring:
Apply a quantile function calculation to this expression.
This is an aggregation that will map to a single value.

Notes:

The quantile function of a given random variable and q value finds the value x where the probability of
   observing a value less than or equal to x is equal to q. See
        https://en.wikipedia.org/wiki/Quantile function
```

Query Scripting – Table Variables

- Any product of select etc can be turned into a table variable with to_table_var
- You don't have to specify a name. Lumipy will automatically generate them.
- Once you have a table variable it can be treated like any other table: you start by chaining select.
- You can also make scalar variables in a similar way.

```
pf = atlas.lusid_portfolio()
```

```
query = tv.select(
         tv.portfolio_scope
).group_by(
         tv.portfolio_scope
).aggregate(
         NumPortfoliosInScope=tv.portfolio_code.count()
)
```

Query Scripting – Windows

- Windows are specified in lumipy using a top-level function in the module
- These correspond to FILTER OVER in SQL. You can specify partitions, ordering and sliding/expanding windows.
- Parameters:
 - lower lower limit of the window given as n rows before current. None = no limit.
 - upper upper limit of the window given as n rows after current limit. None = no limit. Defaults to 0.
 - groups partitions split the window by
 - orders ordering to sort the data by before applying the window
- Filter is specified by chaining the filter method on the window object

```
import lumipy as lm
# default = all rows up to current
window = lm.window()
```

```
# 90 rows before current
lm.window(lower=90)
```

```
# sliding window 10 rows either side
lm.window(lower=10, upper=10)
```

```
# all rows, partition by column
lm.window(groups=table1.col, upper=None)
```

```
fltr_window = window.filter(table1.col > 2)
```

Query Scripting – Window Functions

- Window functions are used by chaining methods on the window objects – just like the table columns
- The windows also have accessor objects that organise the available functions
- All of our statistical functions are window-able, so you can do some sophisticated analyses in sliding/expanding windows that are even partitioned by value

```
import lumipy as lm
w90days = lm.window(lower=90)
```

Query Scripting – Drive and View Creation

EX NB 4

- All queries can be written to drive by using to_drive with a given filepath
- This will write the results to the location in the format specified in the filepath
 - CSV if it ends in .csv
 - Excel if it ends in .xlsx
 - Sqlite if it ends in .sqlite
- You can also read files back out of drive using the drive direct providers
 - drive_csv
 - drive_excel
 - drive_rawtext
 - drive_sqlite
 - drive xml
- Views can be created with create_view on queries and they can be deleted via delete_view on client objects

```
query.create_view('test.less.than.two')
client.delete_view('test.less.than.two')
```



Query Scripting – Joins

- Joins are built using methods on the table objects where you specify the other table and an 'on' condition
- You may also supply aliases for either side of the join. When chaining many joins together you are forced to name them.
- The result will behave like another table which you then call the select method on
- Lumipy will automatically alias any columns with clashing names.
- If you want to join on something you've already selected, filtered, etc. you should convert to a table variable

```
join_table = table1.inner_join(
    table2,
    on=table1.id == table2.id
)
```

```
query = join_table.select('*').limit(10)
```

```
tv = table1.select('*').where(table1.col >
2).to_table_var()

join_table = tv.inner_join(
        table2,
        on=table1.id == table2.id
)
```



Query Scripting – Concat (Unions)

- There is a top-level concat function in lumipy that's analogous to pandas.concat
- This will union together a collection of subqueries
- Particularly useful when scripting:
 - You can create a parameterised set of subqueries with a function and then combine them with concat

```
import pandas as pd

df = pd.concat(list_of_dataframes)
```

```
import lumipy as lm
query = lm.concat(list_of_subqueries)
```

```
def make_subqueries(t_ranges):
    for t1, t2 in t_ranges:
        # do stuff
        yield subquery

query = lm.concat(make_subqueries())
```



Python Providers - Introduction

- There are many great python apps for data science that are an indispensable part of our workflow
- Connecting these to luminesce is the other half of what lumipy does
- We have (experimental) support for writing your own providers in python
- These just require you to inherit from a base class and implement two methods
- There are also pre-built python providers. For example a pandas one that turns dataframes into luminesce providers



Python Providers - Workflow

- The workflow for building and running python providers consists of a few steps
 - Import lumipy.provider
 - Initialise provider classes
 - Build a provider manager
 - Start it all up by calling run on the provider manager
- This will handle spinning things up behind the scenes. All you have to do is make the provider objects and configure the manager
- This will be made available in future as a docker image

```
import lumipy.provider as lp


providers = [
    lp.PandasProvider(df, 'stock.returns'),
    lp.QuadraticProgram()
]

manager = lp.ProviderManager(
    *providers,
    user='<my user id>',
    domain='<my domain>'
)
manager.run()
```



Python Providers – How they Work

- The python provider infrastructure consists of two pieces: the Provider API and the Provider Factory
- The Provider API
 - is a local webserver written in python (FastAPI)
 - It wraps a collection of python provider objects and creates a group of API endpoints for each one
- The Provider Factory:
 - Is a dotnet application that runs at the same time as the API
 - It will start up a luminesce provider for each group of endpoints
 - Once running these providers call out to the underlying python API





Python Providers - Examples

- Three examples:
 - A straightforward pandas dataframe running as a provider
 - An index builder that wraps a quadratic optimisation for allocating weights given some returns data
 - Something completely useless...



Summary


- Lumipy provides a suite of tools for using luminesce and python together
- For getting data from luminesce into the python data science ecosystem you have the atlas and fluent query syntax
- For getting data and result back into luminesce we have the python provider infrastructure



Thank You For Listening!

Any questions?

a panda giving a powerpoint presentation





© FINBOURNE Technology